



Software Release Notes

Software name: Network Configurator

Software number/version: SOFT-00262 / V1.6.0.0

File size: 41.3 MB (43.395.813 bytes)

Release date: February 11, 2022

Download link1: <http://ftp.roctest-group.com:5000/file/sharing/X5GbB6O2I>

Applicable to:

- EasyGrid, EasyGrid-LT and EasyGrid-Base Monitors with Ethernet communication port

Supported Operating Systems:

- Windows 10

Changes:

- Add the parameter " number of reports enabled " to select the number of concurrent connections (1 to 5).
- Add format validation for: IED name and Access Point Name.
- Add Save Config File functionality to save device configuration (for example for the IEC61850 protocol, that will save the ICD file with the configured parameters like IED Name, Access Point Name, etc.)
- For downloading configuration, the file browser now automatically open in the folder corresponding to the detected Ethernet module.
- Added support for a new Ethernet module.

Fixed Issues:

- None.