



FISO Technologies

500 St-Jean-Baptiste Ave., suite 195  
Québec (Québec)  
Canada G2E 5R9

Phone  
(418) 688-8065

Fax  
(418) 688-8067

www.fiso.com  
info@fiso.com

---

# Software Release Notes

---

**Software name:** EasyGrid & EasyGrid-LT, Firmware

**Software number/version:** SOFT-00177 / R4.6.0.0

**File size:** 348KB (356895 bytes)

**Release date:** 2022/04/15

**Download link1:** <https://fiso.com/en/support/> (select folder EasyGrid V1.0)

**Download link2:** <https://fiso.com/en/support/> (select folder EasyGrid LT V1.0)

## Applicable to:

- EasyGrid & EasyGrid-LT, with Firmware SOFT-0177 R4.0.1.0 to R4.5.2.0

## Changes:

- The selection of the communication protocol (Nortech, Modbus or Ethernet) is now made with the EasyGrid Dip Switch #2
- EasyGrid & EasyGrid-LT Ethernet configuration improvement (automatically set the required Modbus parameters to have good Ethernet communication).

## Fixed Issues:

- Intermittent power up issue with the initialization of the EasyGrid System Relay.